

TASP workstation configuration(s):

TASP Server workstation:

Processor : Dual Processor Intel Pentium (P4) 2.53 GHz
Memory RAM : 4 GB
HardDrive Capacity : 136GB
Operating System : Windows 2000 Server Edition
Support Software : JAVA SDK 1.4.2

AAWC, AIC workstations:

Processor : Intel P4 2.53 GHz
Memory RAM : 1 GB
HardDrive Capacity : 80GB
Operating System : Windows XP
Support Software : JAVA SDK 1.4.2

AAWC, AIC Speech Recognizer workstations:

Processor : Intel P4 2.53 GHz
Memory RAM : 1 GB
HardDrive Capacity : 80GB
Operating System : Windows 2000 Professional
Support Software : JAVA SDK 1.4.2,
Nuance v7.0.4,
Nuance Foundation Speech Objects v1.1.1
Language Module English America r1

***Note: Need License from Nuance for Speech Recognizer on all workstations,
(See “startup” document for more details).***

Installation Manual instructions

Hardware Installation:

1. Set up all the machines behind a router and assign the following IP addresses.

TASP Server workstation	= 192.168.1.100
AAWC (TASP & Synther) workstation	= 192.168.1.110
AAWC Speech Recognizer Workstation	= 192.168.1.120
AIC (TASP & Synther) Workstation	= 192.168.1.130
AIC Speech Recognizer Workstation	= 192.168.1.140

Software Installation:

Java SDK1.4.2:

- 1) In the folder \\Downloads\\, double-click “j2sdk-1_4_2_03-windows-i586-p” file to automatically install.
- 2) Online download available at
 - o <http://java.sun.com/j2se/1.4.2/download.html>
- 3) Add the location of the java’s bin directory to the *path* environment variable, to make java available in all directories.
- 4) IMPORTANT NOTE: Please add the character “.”, in *classpath* environment variable
(Refer to Startup document for how to set up environment variables).

Nuance v7.0.4:

- 1) In the folder \\Downloads\\, unzip the file “704-NT.zip”.
- 2) Double-click on “setup.exe” file to automatically install.
IMPORTANT NOTE: Make sure the character “.”, is added in *classpath* environment variable (Refer to Startup document for how to set up environment variables).

Nuance Service Pack 29:

- 1) In the folder \\Downloads\\, unzip the file “NUANCE-7-0-4-SP29-NT.zip” to the %NUANCE% directory.
NOTE: open a command prompt and type “echo %NUANCE%” to get the location of the %NUANCE% directory.

Nuance FSO v1.1.1 (Foundation Speech Objects):

- 1) In the folder \\Downloads\\, unzip the file “FSO-V1.1.1.zip”.
- 2) Double-click on “setup.exe” file to automatically install.

Language Module English America v7-0r1:

- 1) In the folder \\Downloads\\, unzipped the file “LanguageModuleEnglish America r1.zip” to the %NUANCE% directory.

Resources for Nuance available online at:

<http://www.nuance.com>